

# Dryopteris (Brilliance Autumn Fern)

## 20ct Plug

Container:

Trade 1 Gallon Container

Finish:

7-9 weeks

When To Plant:

Mid to late summer or spring

## 72ct Plug

Container:

Trade 1 Gallon Container

Finish:

9-12 weeks

When To Plant:

Mid to late summer

### Growing Temperature:

60-70° F

### EC Level:

1.0-1.5 pour through method

### Pests and Diseases:

Nematodes, aphids, whiteflies, and fern moth caterpillar in greenhouse; thrips, scales, mealybugs, black vine weevil, fern snail (*Deroceras*), armyworms, Japanese beetle, crickets, grasshoppers, caterpillars in the field.

Botrytis blight, leaf spots, sooty mold (indoors or South), rusts, damping-off (of prothalli), foliar *Rhizoctonia*, *Pythium*.

A preventative fungicide drench after planting can be beneficial.

### Moisture:

Good irrigation practices are important. Ferns should be kept moist the entire time they are grown. Water thoroughly when irrigation is required, and allow the substrate to dry slightly between waterings. It is best to water early in the day to allow the fronds plenty of time to dry before night.

### Lighting:

Provide 50% shade in the north and 70% shade in the south.

### Soil pH:

5.5-6.5

### Fertility:

Ferns are sensitive to high salt levels and may become scorched or experience root injury. Apply 50-7 5ppm nitrates delivered through a water soluble fertilizer with every irrigation. Time released fertilizers incorporated in planting media should be about half of that used with most other perennials.

For Controlled Release or Slow Release Fertilizer, see your preferred supplier for recommended rates for incorporation or top dressing, as it varies by fertilizer.

### Potting and Timing:

Ferns can be grown at 65-70 F to flush quicker, then lower the temperatures to 58-63 degrees F to finish the crop.

It is best to plant ferns in the summer and bulk before winter.

### Planting Level:

Plugs should be placed at same level as soil surface in the container.

### Grower Tips:

Ferns should not be planted after mid August, they need an adequate amount of time to become established before wintering over. Optimal temperatures for rooting are 65-70° F.



**WaltersGardens**  
INC

P.O. Box 137 • 1992 96th Ave. Zeeland, MI. 49464

Phone: 888-925-8377 • Fax: 800-752-1879

Email: [sales@waltersgardens.com](mailto:sales@waltersgardens.com)

[www.WaltersGardens.com](http://www.WaltersGardens.com) • [www.PerennialResource.com](http://www.PerennialResource.com)

[www.ProvenWinners.com](http://www.ProvenWinners.com)